



Xplore Technologies Software Release Note

Name	Bobcat BIOS update
File Name	BOBCAT1_BOBCAT2_BIOS_UPDATE_11-16-2016.zip
Release Date	Nov 21, 2016
This Version	BIOS IUHE1AXP EC-1D20 or BIOS IUHE2BXP EC-260A
Replaces Version	All previous versions
Intended Users	All Bobcat users
Intended Product	Bobcat Tablet PCs only
File Size	298 MB
Supported Operating System	Windows 10 (64-bit), Windows 8.1 (64-bit) and Windows 7 (64-bit)

Fixes in this Release

- Fixed Windows 10 on screen keyboard layout

What's New in this Release

- N/A

Installation and Configuration Instructions

Pre-requisite- USB Key (min 512Kb), identify drive letter from File Explorer

Installation:

1. Insert USB key into tablet
2. Note drive letter of USB key from File Explorer
3. Unzip BIOS update package to desktop
4. Open command windows as administrator
5. Navigate to location of the BIOS update package files
6. Execute MakeBIOS_USB.cmd F:
 - a. Insure to use the correct drive letter for USB key. In the above example, the USB Key has been assigned drive letter F:
7. Program will execute and configure your USB key
8. Power down tablets
9. Plug AC power into the tablet
10. Be sure USB key is still in the tablet
11. Power on the tablet and hold down the home key continuously until the BIOS boot menu appears
12. Select you USB Key to boot to
13. Tablet will boot to WinPE then shutdown
14. Tablet will begin to update the BIOS and EC and go through several shutdowns
15. Each time the system powers down, power it back on to continue the process **BE SURE THE USB KEY REMAINS IN THE TABLET THROUGHOUT THE PROCESS!**

16. When process is complete, a green screen will appear indicating success
17. Remove the USB key and power off the tablet
18. Done

Licensing

Refer to your applicable end user licensing agreement for usage terms.